



ProAdmin®
by WinTech

Last updated: 10/6/2025

Grid Platform Installation Guide

For ProAdmin



This document was prepared to assist users of Winklevoss Technologies' ProVal, ProAdmin and Grid Platform Systems; its contents may not be used for any other purpose without written permission. The material contained herein is supplied without representation or warranty of any kind. Winklevoss Technologies therefore assumes no responsibility and shall have no liability arising from the supply or use of this document or the material contained herein.

Copyright © 2025 Winklevoss Technologies, LLC
Printed in the United States of America. All rights reserved.
Unauthorized reproduction is strictly prohibited.

Windows[®] is a registered trademark of Microsoft Corporation.



Contents

OVERVIEW	4
CONFIGURING PROADMIN TO ACCESS THE GRID	5
CREATING GRID AGENTS	6
STARTING GRID AGENTS	7
UNINSTALLING GRID AGENTS	9
APPENDIX A: GRID AGENT SYSTEM REQUIREMENTS	10



Overview

WinTech's Grid Platform allows ProAdmin users to distribute certain CPU intensive ProAdmin runs across a network of computers to achieve faster processing times.


The Grid is created by connecting one or more ProAdmin users to one or more Grid Agents, using a common network folder to pass data packets back and forth. ProAdmin can package and ship executable packets to the common folder, where a listening Agent can fetch the packets, execute that small portion of the run, and ship results back to the shared folder. ProAdmin then fetches all results for a particular run and aggregates them.

By default, the Agent will try to maximize the number of processors it donates to the Grid. This will run the machine's total CPU to close to 100%. Therefore, the Agent is best suited for installation on a dedicated workstation or server computer.

To setup a ProAdmin user to access the Grid you must edit the .ini settings to point to the common network folder.

To add a computer as a Grid agent, you must (1) install the WinTech Grid Agent and (2) edit the Grid Agent INI file to point to the proper network folder. The Agents may run as a Window's Service or an application.

WinTech Grid Platform





Configuring ProAdmin to access the Grid

To allow ProAdmin user's workstations access to the Grid Platform and Grid Agent computers, the following needs to be added to every user's **PROADMIN.INI files**.

```
[Grid]
GridWork=
```

The GridWork directory points to a common network location used to coordinate all Grid Agent computers and all ProAdmin user computers.



NOTE: All computers within the Grid Platform must have read/write/create access to the GridWork directory and must point to the same directory. For optimal performance, it is important that the shared GridWork directory have as low of latency and as high of bandwidth as possible.



```
PROADMIN.INI - Notepad
File Edit Format View Help
[User]
Company=WinTech
UserLevel=99

[grid]
GridWork=\\filesshr\ProAdmin\Grid

[Tables]
; Historical Interest Rate Tables
; HIRTcode has two options 1=read from an Access database and
```



Creating Grid Agents



NOTE: WinTech's Grid Platform is compatible with ProAdmin version 3.05 and later.

1. Obtain and install the Grid Agent Installation Program

Visit <https://www.wintech.com/proadmin/downloads/> and click the "Download Grid Agent Installation" button to download the installation program, WinTechGridAgent.exe. On some systems, the .exe extension is stripped off for security reasons – in those cases, simply rename the file with an .MSI extension.

Run the Grid Agent installation program (WintechGridAgent.msi) and follow the instructions.

By default the installation will install the program in the folder C:\WinTech\Grid. If you choose to override the default directory, be absolutely sure there are no access restrictions to that directory. Do not install under the Program Files folder.



NOTE: Version 3.07 of the install program does not uninstall a previous 3.06 version. If you plan to replace the 3.06 version, you should first uninstall that version using Control Panel | Programs and Features.

2. Edit the GRID.INI file located in the installation directory.

Within the [Grid] section you must specify the GridWork directory. The GridWork directory points to a common network folder to be used to coordinate all Grid Agent computers and all ProAdmin user computers.



NOTE: All computers within the Grid Platform must have read/write/create access to the GridWork directory.


NOTE: When installing the Grid Agent as a service, use only UNC (i.e., of the form \\server\share\) to refer to network paths – mapped drives are not acceptable.

Starting Grid Agents


The Grid Agent can be setup to run as a Windows Service or an Application. Running as a Windows Service is the preferred method for deploying production applications. A Service can be setup to automatically start on boot up and saves with it log on credentials to avoid anyone needing to physically log onto the machine.

Running the Grid Agent as a Service

1. Navigate to your list of Services and locate the "WinTech Grid Agent" Service. Ensure that the Startup Type is set to "Automatic", which ensures that the Service is started automatically every time the Grid Agent machine restarts.



2. In most cases, you will need to configure the Service to use a Log On that has write access to the GridWork folder. Select the "Log On" tab and modify the "Log On As" setting with a fully-qualified username and password as shown below:



3. To start the Service, select the "General" tab and click the "Start" button. Check the Microsoft Windows Event Viewer to ensure that the service is functional.



NOTE: Noteworthy events and handy troubleshooting information for the Service may be viewed in the Windows Event Viewer under the Application Log.

Running the Grid Agent as an Application


To start the Grid Agent to be run as an Application, navigate to the Grid Agent installation directory and double click on WinTechServiceGrid.exe.



Uninstalling Grid Agents

To uninstall the Grid Agent:

1. Click the Start button, point to Settings, and click Control Panel.
2. Double-click the Add/Remove Programs icon.
3. Select WinTech Grid Agent in the list of software and click the Add/Remove button.
4. Note that uninstalling the grid does not remove the Grid.ini and WinTechGridAgent.ini files from the installation folder. This allows uninstall and reinstall the Grid Agent without losing previous settings. But if you have a corrupted or improperly configured ini file, reinstalling will not rectify this because it does not replace these files with new, default versions. So if you want to start over from scratch, you will need to manually eliminate the ini files before reinstalling the Grid Agent to return to a default configuration.





Appendix A: Grid Agent System Requirements

SYSTEM REQUIREMENTS



OPERATING ENVIRONMENT

Microsoft Windows 10 Family.
Microsoft Windows 11 Family.
Microsoft Windows Server 2016 Family.
Microsoft Windows Server 2019 Family.
Microsoft Windows Server 2022 Family.



PROCESSOR*

Intel Pentium[®] 4 3.0 Ghz./256K/533 MHz. FSB (min.)
Dual Intel Xeon[®] 3.2 Ghz./2MB/800 MHz. FSB (rec.)



MEMORY*

2+ GB of available memory is recommended per processor with a minimum of 4GB.



DISK SPACE

20 MB (for actual Grid program files)
If GridWork is located on the Grid Agent machine, then perhaps an additional 5+ GB depending on the volume of activity.



NETWORK CARD

10/100/1000 Mbps Network Card. Producing as low of latency and as high of bandwidth as possible.

* **NOTE:** Requirements vary significantly based on usage.